

Waveform Template

This template is the instrument's response to a command of the form "TMPL?":

```
/00
000000
                    LECROY_2_2: TEMPLATE
                    8 66 111
; Explanation of the formats of waveforms and their descriptors on the
; LeCroy Digital Oscilloscopes,
      Software Release 44.1.1.1, 94/04/18.
; A descriptor and/or a waveform consists of one or several logical data blocks
; whose formats are explained below.
; Usually, complete waveforms are read: at the minimum they consist of
        the basic descriptor block WAVEDESC
        a data array block.
; Some more complex waveforms, e.g. Extrema data or the results of a Fourier
; transform, may contain several data array blocks.
; When there are more blocks, they are in the following sequence:
        the basic descriptor block WAVEDESC
        the history text descriptor block USERTEXT (may or may not be present)
        the time array block (for RIS and sequence acquisitions only)
        data array block
        auxiliary or second data array block
; In the following explanation, every element of a block is described by a
; single line in the form
; <byte position> <variable name>: <variable type> ; <comment>
  where
   <byte position> = position in bytes (decimal offset) of the variable,
                      relative to the beginning of the block.
   <variable name> = name of the variable.
   <variable type> = string
                                    up to 16-character name
                                      terminated with a null byte
                        byte
                                     8-bit signed data value
                                    16-bit signed data value
                        word
                        long
                                    32-bit signed data value
                       float
                                    32-bit IEEE floating point value
```

```
with the format shown below
                                    31 30 .. 23 22 ... 0
                                                              bit position
                                        exponent fraction
                                    where
                                    s = sign of the fraction
                                    exponent = 8 bit exponent e
                                    fraction = 23 bit fraction f
                                    and the final value is
                                    (-1)**s * 2**(e-127) * 1.f
                      double
                                    64-bit IEEE floating point value
                                    with the format shown below
                                    63 62 .. 52 51 ... 0
                                                             bit position
                                        exponent fraction
                                    where
                                    s = sign of the fraction
                                    exponent = 11 bit exponent e
                                    fraction = 52 bit fraction f
                                    and the final value is
                                    (-1)**s * 2**(e-1023) * 1.f
                                    enumerated value in the range 0 to N
                        enum
                                    represented as a 16-bit data value.
                                    The list of values follows immediately.
                                    The integer is preceded by an _.
                  time_stamp
                                    double precision floating point number,
                                    for the number of seconds and some bytes
                                    for minutes, hours, days, months and year.
                                                        (0 to 59)
                                    double seconds
                                                        (0 to 59)
                                    byte
                                            minutes
                                                        (0 to 23)
                                    byte
                                            hours
                                    byte
                                            days
                                                        (1 to 31)
                                                        (1 to 12)
                                    byte
                                            months
                                    word
                                                        (0 to 16000)
                                            year
                                    word
                                            unused
                                    There are 16 bytes in a time field.
                        data
                                    byte, word or float, depending on the
                                    read-out mode reflected by the WAVEDESC
                                    variable COMM_TYPE, modifiable via the
                                    remote command COMM_FORMAT.
                        text
                                    arbitrary length text string
                                    (maximum 160)
             unit_definition
                                    a unit definition consists of a 48 character
                                    ASCII string terminated with a null byte
                                    for the unit name.
WAVEDESC: BLOCK
```

```
; Explanation of the wave descriptor block WAVEDESC;
;
  0>
              DESCRIPTOR_NAME: string ; the first 8 chars are always WAVEDESC
<
< 16>
              TEMPLATE_NAME: string
< 32>
              COMM_TYPE: enum
                                       ; chosen by remote command COMM_FORMAT
                      byte
              _0
              _1
                       word
               endenum
< 34>
              COMM ORDER: enum
              _0 _
                      HIFIRST
                       LOFIRST
              _1
              endenum
; The following variables of this basic wave descriptor block specify
; the block lengths of all blocks of which the entire waveform (as it is
; currently being read) is composed. If a block length is zero, this
; block is (currently) not present.
;BLOCKS :
< 36>
              WAVE_DESCRIPTOR: long
                                      ; length in bytes of block WAVEDESC
< 40>
                                        ; length in bytes of block USERTEXT
              USER_TEXT: long
< 44>
              RES_DESC1: long
; ARRAYS :
< 48>
              TRIGTIME_ARRAY: long
                                       ; length in bytes of TRIGTIME array
< 52>
              RIS_TIME_ARRAY: long
                                        ; length in bytes of RIS_TIME array
< 56>
              RES_ARRAY1: long
                                        ; an expansion entry is reserved
< 60>
              WAVE_ARRAY_1: long
                                        ; length in bytes of 1st simple
                                        ; data array. In transmitted waveform,
                                        ; represent the number of transmitted
                                        ; bytes in accordance with the NP
                                        ; parameter of the WFSU remote command
                                        ; and the used format (see COMM_TYPE).
< 64>
              WAVE_ARRAY_2: long
                                        ; length in bytes of 2nd simple
                                        ; data array
;
```

```
< 68>
               RES_ARRAY2: long
< 72>
               RES_ARRAY3: long
                                         ; 2 expansion entries are reserved
; The following variables identify the instrument
< 76>
               INSTRUMENT_NAME: string
< 92>
               INSTRUMENT_NUMBER: long
< 96>
               TRACE_LABEL: string
                                        ; identifies the waveform.
<112>
               RESERVED1: word
               RESERVED2: word
<114>
                                        ; 2 expansion entries
; The following variables describe the waveform and the time at
; which the waveform was generated.
<116>
               WAVE_ARRAY_COUNT: long
                                        ; number of data points in the data
                                         ; array. If there are two data
                                        ; arrays (FFT or Extrema), this number
                                        ; applies to each array separately.
<120>
               PNTS_PER_SCREEN: long
                                        ; nominal number of data points
                                        ; on the screen
<124>
               FIRST_VALID_PNT: long
                                        ; count of number of points to skip
                                        ; before first good point
                                         ; FIRST_VALID_POINT = 0
                                        ; for normal waveforms.
<128>
               LAST_VALID_PNT: long
                                        ; index of last good data point
                                         ; in record before padding (blanking)
                                        ; was started.
                                        ; LAST_VALID_POINT = WAVE_ARRAY_COUNT-1
                                         ; except for aborted sequence
                                         ; and rollmode acquisitions
·
<132>
               FIRST_POINT: long
                                        ; for input and output, indicates
                                         ; the offset relative to the
                                         ; beginning of the trace buffer.
                                         ; Value is the same as the FP parameter
                                        ; of the WFSU remote command.
<136>
               SPARSING_FACTOR: long
                                        ; for input and output, indicates
                                        ; the sparsing into the transmitted
                                        ; data block.
                                         ; Value is the same as the SP parameter
                                         ; of the WFSU remote command.
```

```
<140>
               SEGMENT_INDEX: long
                                        ; for input and output, indicates the
                                        ; index of the transmitted segment.
                                        ; Value is the same as the SN parameter
                                        ; of the WFSU remote command.
<144>
               SUBARRAY COUNT: long
                                        ; for Sequence, acquired segment count,
                                        ; between 0 and NOM_SUBARRAY_COUNT
<148>
               SWEEPS_PER_ACQ: long
                                        ; for Average or Extrema,
                                        ; number of sweeps accumulated
                                        ; else 1
<152>
               POINTS_PER_PAIR: word
                                        ; for Peak Dectect waveforms (which always
                                        ; include data points in DATA_ARRAY_1 and
                                        ; min/max pairs in DATA_ARRAY_2).
                                        ; Value is the number of data points for
                                        ; each min/max pair.
<154>
               PAIR OFFSET: word
                                        ; for Peak Dectect waveforms only
                                        ; Value is the number of data points by
                                        ; which the first min/max pair in
                                        ; DATA_ARRAY_2 is offset relative to the
                                        ; first data value in DATA_ARRAY_1.
<156>
               VERTICAL_GAIN: float
<160>
               VERTICAL_OFFSET: float
                                        ; to get floating values from raw data :
                                        ; VERTICAL_GAIN * data - VERTICAL_OFFSET
<164>
               MAX_VALUE: float
                                        ; maximum allowed value. It corresponds
                                        ; to the upper edge of the grid.
<168>
               MIN_VALUE: float
                                        ; minimum allowed value. It corresponds
                                        ; to the lower edge of the grid.
<172>
               NOMINAL_BITS: word
                                        ; a measure of the intrinsic precision
                                        ; of the observation: ADC data is 8 bit
                                             averaged data is 10-12 bit, etc.
<174>
               NOM_SUBARRAY_COUNT: word ; for Sequence, nominal segment count
                                        ; else 1
<176>
               HORIZ_INTERVAL: float
                                        ; sampling interval for time domain
                                        ; waveforms
<180>
               HORIZ_OFFSET: double
                                        ; trigger offset for the first sweep of
                                        ; the trigger, seconds between the
                                        ; trigger and the first data point
```

```
<188>
               PIXEL_OFFSET: double
                                        ; needed to know how to display the
                                        ; waveform
<196>
               VERTUNIT: unit_definition ; units of the vertical axis
<244>
               HORUNIT: unit_definition ; units of the horizontal axis
<292>
               RESERVED3: word
<294>
               RESERVED4: word
                                        ; 2 expansion entries
<296>
               TRIGGER_TIME: time_stamp ; time of the trigger
<312>
               ACQ_DURATION: float
                                        ; duration of the acquisition (in sec)
                                        ; in multi-trigger waveforms.
                                        ; (e.g. sequence, RIS, or averaging)
<316>
               RECORD_TYPE: enum
               _0
                       single_sweep
               _1
                       interleaved
                       histogram
                       graph
                       filter_coefficient
                       complex
                       extrema
                       sequence_obsolete
                       centered_RIS
                       peak_detect
               endenum
;
<318>
               PROCESSING_DONE: enum
               _0
                        no_processing
                        fir filter
                        interpolated
                        sparsed
                        autoscaled
                        no_result
                        rolling
                        cumulative
               endenum
<320>
               RESERVED5: word
                                        ; expansion entry
<322>
               RIS_SWEEPS: word
                                        ; for RIS, the number of sweeps
                                        ; else 1
; The following variables describe the basic acquisition
; conditions used when the waveform was acquired
```

```
<324>
               TIMEBASE: enum
               _0
                      1_ps/div
               _1
                      2_ps/div
               _2
_3
_4
_5
_6
_7
_8
                      5_ps/div
                      10_ps/div
                      20_ps/div
                      50_ps/div
                      100_ps/div
                      200_ps/div
                      500_ps/div
                      1_ns/div
               _9
               _
_10
                     2_ns/div
               _11
                      5_ns/div
                      10_ns/div
               _12
               _13
                      20_ns/div
               _14
                      50_ns/div
                      100_ns/div
               _15
                      200_ns/div
               _16
               _17
                     500_ns/div
                      1_us/div
               _18
               _19
                     2_us/div
               _20
                      5_us/div
               _21
                      10_us/div
               _22
                      20_us/div
                     50_us/div
               _23
               _24
                      100_us/div
               _25
                      200_us/div
               _26
                     500_us/div
               _27
                      1_ms/div
                      2_ms/div
               _28
               _29
                      5_ms/div
               _30
                     10_ms/div
                      20_ms/div
               _31
                      50_ms/div
               _32
               _33
                      100_ms/div
               _34
                      200_ms/div
                      500_ms/div
               _35
               _36
                      1_s/div
               _37
                      2_s/div
               _38
                      5_s/div
               _39
                     10_s/div
               _40
                      20_s/div
                     50_s/div
               _41
               _42
                      100_s/div
               _43
                      200_s/div
               _44
                      500_s/div
                      1_ks/div
               _45
               _46
                      2_ks/div
```

Template

```
_47
                     5_ks/div
              _100 EXTERNAL
              endenum
<326>
              VERT_COUPLING: enum
                      DC_50_Ohms
              _0
              _1
                      ground
              _
_2
_3
                      DC_1MOhm
                      ground
              _4
                      AC,_1MOhm
              endenum
<328>
              PROBE_ATT: float
<332>
              FIXED_VERT_GAIN: enum
              _0 1_uV/div
              _1 2_uV/div
_2 5_uV/div
              _3 10_uV/div
              _5
_6
_7
_8
_9
                   20_uV/div
                   50_uV/div
                   100_uV/div
                   200_uV/div
                   500_uV/div
                   1_mV/div
              _10 2_mV/div
              _12 10_mV/div
              _13 20_mV/div
              _14 50_mV/div
              _15 100_mV/div
_16 200_mV/div
              _17 500_mV/div
              _18 1_V/div
              _19 2_V/div
              _20 5_V/div
              _21 10_V/div
              _22 20_V/div
              _23 50_V/div
              _24 100_V/div
              _25 200_V/div
               _27 1_kV/div
              {\tt endenum}
<334>
              BANDWIDTH_LIMIT: enum
              _0
                      off
```

_1

on

```
endenum
<336>
           VERTICAL_VERNIER: float
<340>
           ACQ_VERT_OFFSET: float
<344>
           WAVE_SOURCE: enum
           _0
                  CHANNEL_1
                  CHANNEL_2
           _1
           _2
                  CHANNEL_3
           _3
                  CHANNEL 4
            _9
                  UNKNOWN
           {\tt endenum}
/00
             ENDBLOCK
USERTEXT: BLOCK
; Explanation of the descriptor block USERTEXT at most 160 bytes long.
< 0>
           TEXT: text
                               ; a list of ASCII characters
/00
             ENDBLOCK
DATA_ARRAY_1: ARRAY
; Explanation of the data array DATA_ARRAY_1.
; This main data array is always present. It is the only data array for
; most waveforms.
; The data item is repeated for each acquired or computed data point
; of the first data array of any waveform.
< 0>
           MEASUREMENT: data
                               ; the actual format of a data is
                               ; given in the WAVEDESC descriptor
                               ; by the COMM_TYPE variable.
/00
             ENDARRAY
DATA_ARRAY_2: ARRAY
; Explanation of the data array DATA_ARRAY_2.
; This is an optional secondary data array for special types of waveforms:
```

```
(real part in DATA_ARRAY_1)
      Complex FFT
                    imaginary part
;
      Extrema
                    floor trace
                                     (roof trace in DATA_ARRAY_1)
      Peak Detect
                    min/max pairs
                                     (data values in DATA_ARRAY_1)
; In the first 2 cases, there is exactly one data item in DATA_ARRAY_2 for
; each data item in DATA_ARRAY_1.
; In Peak Detect waveforms, there may be fewer data values in DATA_ARRAY_2,
; as described by the variable POINTS_PER_PAIR.
            MEASUREMENT: data
                                  ; the actual format of a data is
                                  ; given in the WAVEDESC descriptor
                                  ; by the COMM TYPE variable.
/00
              ENDARRAY
TRIGTIME: ARRAY
; Explanation of the trigger time array TRIGTIME.
; This optional time array is only present with SEQNCE waveforms.
; The following data block is repeated for each segment which makes up
; the acquired sequence record.
            TRIGGER_TIME: double
                                  ; for sequence acquisitions,
                                  ; time in seconds from first
                                  ; trigger to this one
< 8>
            TRIGGER_OFFSET: double
                                 ; the trigger offset is in seconds
                                  ; from trigger to zeroth data point
/00
              ENDARRAY
RISTIME: ARRAY
; Explanation of the random-interleaved-sampling (RIS) time array RISTIME.
; This optional time array is only present with RIS waveforms.
; This data block is repeated for each sweep which makes up the RIS record
< 0>
            RIS_OFFSET: double
                                 ; seconds from trigger to zeroth
                                  ; point of segment
/00
              ENDARRAY
SIMPLE: ARRAY
```

```
; Explanation of the data array SIMPLE.
; This data array is identical to DATA_ARRAY_1. SIMPLE is an accepted
; alias name for DATA_ARRAY_1.
              MEASUREMENT: data
< 0>
                                       ; the actual format of a data is
                                       ; given in the WAVEDESC descriptor
                                       ; by the COMM_TYPE variable.
/00
                ENDARRAY
DUAL: ARRAY
; Explanation of the DUAL array.
; This data array is identical to DATA_ARRAY_1, followed by DATA_ARRAY_2.
; DUAL is an accepted alias name for the combined arrays DATA_ARRAY_1 and
; DATA_ARRAY_2 (e.g. real and imaginary parts of an FFT).
              MEASUREMENT_1: data
                                      ; data in DATA_ARRAY_1.
< 0>
              MEASUREMENT_2: data
                                      ; data in DATA_ARRAY_2.
/00
                ENDARRAY
000000
                    ENDTEMPLATE
```

#



BLANK PAGE